RTI Connext DDS

Core Libraries

Getting Started Guide

Addendum for iOS Systems

Version 5.3.0



© 2017 Real-Time Innovations, Inc.
All rights reserved.
Printed in U.S.A. First printing.
June 2017.

Trademarks

Real-Time Innovations, RTI, NDDS, RTI Data Distribution Service, DataBus, Connext, Micro DDS, the RTI logo, 1RTI and the phrase, "Your Systems. Working as one," are registered trademarks, trademarks or service marks of Real-Time Innovations, Inc. All other trademarks belong to their respective owners.

Copy and Use Restrictions

No part of this publication may be reproduced, stored in a retrieval system, or transmitted in any form (including electronic, mechanical, photocopy, and facsimile) without the prior written permission of Real-Time Innovations, Inc. The software described in this document is furnished under and subject to the RTI software license agreement. The software may be used or copied only under the terms of the license agreement.

Technical Support

Real-Time Innovations, Inc. 232 E. Java Drive Sunnyvale, CA 94089 Phone: (408) 990-7444

Email: support@rti.com

Website: https://support.rti.com/

Contents

Chapter 1 Installing Connext DDS and Xcode	1
Chapter 2 Creating an Xcode Project	2
Chapter 3 Generating Example Code and an Xcode Project with rtiddsgen	
3.1 About the Generated Code	5
Chapter 4 Executing the Code	6

Chapter 1 Installing Connext DDS and Xcode

This document supplements the <u>RTI Connext DDS Core Libraries Getting Started Guide</u> with additional steps for working with iOS® platforms.

• To install the Xcode® development software:

Download the software from the Apple® App Store® or developer website and follow the instructions.

• To install Connext DDS:

Follow the installation instructions in the <u>RTI Connext DDS Core Libraries Getting Started Guide</u>. Install the desired iOS architecture package(s).

Chapter 2 Creating an Xcode Project

1. Create a new iOS Project of whatever type is appropriate for your use case.

Follow instructions on the <u>Apple Developer's website (https://developer-apple.com/library/ios/recipes/xcode_help-structure_navigator/articles/Creating_a_Project.html#//apple_ref/doc/uid/TP40009934-CH3-SW1)</u>

- 2. Add the Connext DDS core to your project:
 - a. Select the project and go to the **Build Settings** tab.
 - b. Add the path to the Connext DDS include files.

/Applications/rti_connext_dds-x.y.z/include /Applications/rti_connext_dds-x.y.z/include/ndds




c. Add preprocessor definitions

Add the RTI_UNIX preprocessor declaration and compiler option —Wno-return-type-c-linkage.



d. Add the Connext DDS Libraries

To add the Connext DDS libraries, right-click on the project and select **Add Files to "<project name>"** or add them in the 'Link Binary With Libraries' section of the 'Build Phases' tab and choose **Add Other...** Either method will lead to a selection dialog like this:



Select the Connext DDS libraries for your architecture and language. All languages require **libnddscore** and **libnddsc**. For C++, add **libnddscpp**; etc. (see the iOS section of the *Platform Notes*). If you want to use any of the C++ APIs, rename the Xcode-generated **ViewController.m** source file (or whatever source file you use to call Connext DDS) to **ViewController.mm**.

3. Call the Connext DDS API

Call the Connext DDS *Entity* creation APIs (**create_participant(**), **create_topic(**), etc.) as described in the <u>RTI Connext DDS Core Libraries Getting Started Guide</u>. In the appropriate locations in your code, call the read and write operations.

4. Access the QoS files

Connext DDS locates the Quality of Service (QoS) XML file using a number of search paths (see the *User's Manual*). The Xcode development software transfers files to the target device via a settings bundle.

- a. Create a **Settings.bundle** resource following Apple's instructions, then place the QoS file(s) in the **Settings.bundle** folder.
- b. In your application code, do one of the following:
 - Set NDDS QOS PROFILES to the QoS file in the application's resource path.
 - Change the default directory to the application's resource bundle path.
 - Copy the QoS file(s) to the application's **documents** directory and change the default directory to the application's **documents** directory.

Chapter 3 Generating Example Code and an Xcode Project with rtiddsgen

1. Run rtiddsgen:

From a terminal or ssh window, run *rtiddsgen* as per other Connext DDS architectures specifying the iOS architecture name.

2. Open the generated workspace or project:

rtiddsgen creates a workspace with two project files, one for the publisher and one for the subscriber. Open the workspace or project with the Xcode development software just as you would open any other Xcode project.

3.1 About the Generated Code

The code generated by *rtiddsgen* for iOS is slightly different than the code generated for other architectures.

- For most architectures, the main function, looping, and messaging are controlled completely by the application. However for an iOS architecture, the main event loop is within the operating environment framework.
- For an iOS architecture, the default output from **print()** goes to the debugger window.

It is important not to do any lengthy processing in the main loop of an iOS application. For this reason, the generated publisher code writes on a timer rather than in a 'for' loop with a sleep. Since the generated subscriber code uses *Waitsets* and data is received in a middleware thread, the changes to the subscriber code are minimal. The generated subscriber project contains commented-out code that can redirect Connext DDS core messages to a text window. To enable this code, define REDIRECT_LOGGING before building the application.

The generated examples place a default QoS file in the **Settings.bundle** folder and set the application's default directory to the resource path. (See Access the QoS files (Section on page 4)).

Chapter 4 Executing the Code

Execute the application via the Xcode development software, just as you would execute any other iOS application.